
Razer (Fiuu)

- Fiuu Setup Guide
- FIUU Static QR Download
- Fiuu OPA Setup Guide


Fiuu Setup Guide

Login

1) Open Fiuu Portal URL: https://portal.fiuu.com/index.php?mod=authentication&opt=login . Enter **Merchant ID, email** and **password** to Login




2) Select **Yes, I want to login!**



New Account Setup


1) If it is a new account, have to set **Return URL**, **Notification URL**, and **Callback URL**. From Sidebar, under **Transactions**, select **Settings,** enter the URL




Return URL, Notification URL and Callback URL:

https://payment-engine.antlysis.com/api/payment/razer/success


2) You also can set the Return URL, Notification URL and Callback URL in this page. From Sidebar, Under **Settings**, select **Transaction Settings.** Click the pencil icon to edit the URL



3) To register the domain, from sidebar, under **Settings** select **Profile Settings**




4) Enter the domain name (**payment-engine.antlysis.com**) and click **Register** button




Config Setup


1) From Sidebar under **Home**, you can copy the **Merchant ID**, **Verify Key** and **Secret Key**, then paste into Laundro Portal




2) In Laundro Portal, go to Settings Page, under Payment Gateway Config, select **Add Razer Config**




3) Enter the Label, paste the Merchant ID, Verify Key and Secret Key, then click **Submit** button







4) Enter the Label, paste the Merchant ID, Verify Key and Secret Key, then click **Submit** button.



5) To enable Fiuu in machine payment (static DuitNow and ewallet), in outlet settings page, under **Payment Gateway Config**, select the token config.




6) Payment Gateway select **Razerpay**, and select the **Razer Config**, then click **Submit** button.




7) To complete this process, the outlet details need to be updated in the payment configuration.


8) Go to ''**My Outlet**''




9) Select the outlet for which you want to update the payment configuration.




10) Click “Edit Outlet”.



11) Click “Next” until you reach the Payment Configuration section.






13) Click ''**Save**'' and its done.


FIUU Static QR Download

Login

1) Open Fiuu Portal URL: https://portal.fiuu.com/index.php?mod=authentication&opt=login . Enter **Merchant ID, email** and **password** to Login




2) Select **Yes, I want to login!**





Static DuitNow QR Code

1) In Fiuu Portal, from sidebar, under **Payment Link**, select **Generate Static QR-Code.**




2) Click on “Channel” and select “DuitNow QR Offline”. After selecting it, the configuration will change to “Type2”.







3) Select the currency and enter the Machine ID in the “Order ID / Item ID” column, then click on “Generate Preview”.



4) After clicking “Generate Preview”, a QR code will be generated. Below the QR code, click “Save”.



5) After clicking “Save”, scroll down and you will see three icons on the right. Click on the middle icon to preview and download the QR code.



6) Click the **Download QR Code** button to donwload the QR code




Machine ID


1) You can get the ''**Machine ID**'' from Laundro Portal in the machine settings page.

Step 1: Go to **“My Outlets”.**

Step 2: Select the specific outlet.



Step 3: Click on “**Machine**” and copy the ID highlighted in the circle.



Fiuu OPA Setup Guide

Step 1: Request OPA Credentials from Fiuu Support

Send an email to support@fiuu.com to request an Offline Payment API (OPA) application for our existing merchant account.

Email Subject: Request for OPA Application and DuitNow QR Enablement

Email Body:

Hi Fiuu Team,

We're an existing Fiuu merchant with the following details:

- **Merchant ID:**

Please assist with the following requests:

1. Create an Offline Payment API (OPA) application for our merchant account.
2. Provide the Application Code and Secret Key required for integration.
3. Enable DuitNow QR (Channel 24) for the Pre-Create QR functionality.

Please let us know once the application has been created and the requested payment channel has been enabled.

Thank you.

Expected Response from Fiuu

Fiuu Support should provide the following information:


- Application Code
- Secret Key
- Confirmation that DuitNow QR (Channel 24) is enabled for Pre-Create QR

Record the credentials in the designated Excel configuration file and handle the Secret Key securely.

Step 2: Add the Fiuu Payment Gateway in Laundro

Once Fiuu Support has provided the required credentials, configure the payment gateway in the Laundro system.

1. Log in to the Laundro system.
2. Navigate to **Settings** from the right-hand profile menu.
3. Open the payment gateway configuration section.
4. Click **Add Payment Gateway** to view the available payment gateway options.
5. Select **Razer (Fiuu) Offline Payment API** from the list of available gateways.
6. Click **Next** to open the gateway configuration form.



Step 2.1: Configure the Payment Gateway

On the **Razer (Fiuu) Offline Payment API** configuration page, enter the following details:

Field	Description

Label	Enter a descriptive name for the payment gateway, such as `Fiuu OPA`.
Application Code	Enter the Application Code provided by Fiuu Support and recorded in the Excel configuration file.
Secret Key	Enter the Secret Key provided by Fiuu Support and recorded in the Excel configuration file.

7. Verify that the Application Code and Secret Key match the details provided by Fiuu Support.
8. Click **Submit** to save the payment gateway configuration.
9. Confirm that the gateway has been added successfully.

Important: Keep the Secret Key confidential. Do not include its actual value in this documentation or share it through unsecured channels.

