

Short Running Cycle

When we check the data in the transaction record, we found a Short Running Cycle as shown [in the image].

<input type="checkbox"/>	SURIA 2	DLS2-W1	2	0.08	0.00	0.00	0.00	2025-10-30	02:12:38	02:12:43	other	⊘
<input type="checkbox"/>	SURIA 2	DLS2-W1	2	0.17	0.00	0.00	0.00	2025-10-30	02:12:48	02:12:58	other	⊘
<input type="checkbox"/>	SURIA 2	DLS2-W1	2	0.17	0.00	0.00	0.00	2025-10-30	02:13:03	02:13:13	other	⊘
<input type="checkbox"/>	SURIA 2	DLS2-W1	2	0.08	0.00	0.00	0.00	2025-10-30	02:13:18	02:13:23	other	⊘
<input type="checkbox"/>	SURIA 2	DLS2-W1	2	0.25	0.00	0.00	0.00	2025-10-30	02:13:28	02:13:43	other	⊘
<input type="checkbox"/>	SURIA 2	DLS2-W1	2	0.17	0.00	0.00	0.00	2025-10-30	02:13:48	02:13:58	other	⊘
<input type="checkbox"/>	SURIA 2	DLS2-W1	2	0.17	0.00	0.00	0.00	2025-10-30	02:14:08	02:14:18	other	⊘

<input type="checkbox"/>	MANGGA	MGA-D8	3	1.42	0.00	0.00	0.00	2025-10-24	05:40:48	05:42:13	dryer
<input type="checkbox"/>	MANGGA	MGA-D8	3	1.17	0.00	0.00	0.00	2025-10-24	05:43:43	05:44:53	dryer
<input type="checkbox"/>	MANGGA	MGA-D8	3	1.43	0.00	0.00	0.00	2025-10-24	05:45:48	05:47:14	dryer
<input type="checkbox"/>	MANGGA	MGA-D8	3	0.17	0.00	0.00	0.00	2025-10-24	05:47:59	05:48:09	dryer
<input type="checkbox"/>	MANGGA	MGA-D8	3	0.83	0.00	0.00	0.00	2025-10-24	05:48:34	05:49:24	dryer
<input type="checkbox"/>	MANGGA	MGA-D8	3	1.75	0.00	0.00	0.00	2025-10-24	05:50:14	05:51:59	dryer
<input type="checkbox"/>	MANGGA	MGA-D8	3	0.58	0.00	0.00	0.00	2025-10-24	05:53:14	05:53:49	dryer

Threshold

1. After configure, observe the threshold menu for each device at the configuration page.
2. The default "Threshold" value is set to 0.8. However you should increase or decrease the value based on its idle value.



Wire Harness

1. Make sure the connection is tight by checking the wire harness and screw terminal.



Revision #13

Created 4 November 2025 02:57:35 by Sulaiza

Updated 5 November 2025 23:56:40 by Sulaiza